

FxMath AI Trader Gold

Dear Traders,

Thank you for purchasing the FxMath AI Trader Gold EA. This EA is powered by artificial intelligence and uses a machine learning strategy to place and manage trades automatically, making it 100% hands-free. To ensure optimal performance, we recommend running the EA on a virtual private server (VPS) to maintain uninterrupted access to the trading platform 24/5.

Installing the FxMath AI Trader Gold EA is a simple process. First, copy the FxMath_AI_Base_Trader_Gold.ex4 file to your MT4 Experts folder. Next, enable DLL imports in the Tools menu of your MT4. Then, register your MT4 account number on this page: <https://fxmath.com/lpm/dashboard/index.php>.

To attach the EA to a chart, open a naked chart in your MT4 and add the EA. Please note that it may take a few hours for the EA to start trading. Also, make sure that the "Auto Trading" tab is enabled in your MT4.

We offer some simple settings that you can adjust to suit your trading preferences. You can modify your lot size, set a hard stop loss/take profit, and enable trailing and breakeven functions.

For each \$200 deposit, we recommend using a lot size of 0.01. However, running the EA on a \$100 account with a lot size of 0.01 is also acceptable.

When you enable the `Trailing_Enable` setting, the EA will begin trailing your profits. To activate this feature, set `Trailing_Enable` to true and adjust your `Trailing_Percent` value. A value of 100 means that the EA will not trail your profits. The default value is 30%, which means that the EA will trail your profits by 30% of the distance between the `OpenPrice` and `TakeProfit` levels.

For example, if your `TakeProfit` is 120 pips, 30% of 120 is 40 pips. This means that the EA will trail your profits with a distance of 40 pips from the current market price when your trade is in profit.

To enable the `BreakEven` function, change the `BE_Enable` setting to true. We also offer a `BE_Ratio_Percent` setting, which determines when the EA will move the `Hard StopLoss` to the `OpenPrice` of the trade.

When the price goes into profit and reaches the `BE_Ratio_Percent` level (as a percentage of the distance between the `TakeProfit` and `OpenPrice`), the EA will move the `Hard StopLoss` to the `OpenPrice` of the trade.

For more information please visit:

Email: fxmath@fxmath.com

Website: <https://www.fxmath.com>

TelegramGroup: <https://t.me/FxMathAI>